

Software Update Process

An Internet connection is required to download and install MiniVision updates. To update your device, go to “Settings”, select "About Phone" and then "System Updates". Select "Download and install" and press the "OK" button to start the download.

Depending on your connection, downloading the update may take some time. When the download is complete, select "Install" from the system update screen. It may take a few minutes to complete the process before you could use the product (vocalized feedback).

System improvements:

- **Overview:**
 - Bugs fix and performance improvement
 - Translation and vocalization improvement
 - New Croatian language available
- **System:**
 - Possibility to upgrade the software through 3G / 4G network.
 - Possibility to call Emergency phone number (i.e. 112 or 911) from PIN code screen and screen lock screen from Menu key.
 - New option to set the time zone (See Settings / Date & Time)
- **Accessibility :**
 - A new font has been added in Settings > Display> Font. The typeface "Luciole" was designed specifically for the visually impaired
- **Edit Box:**
 - Automatic upper case at the beginning of the sentence, and after a period symbol.
 - Correction of the unsolicited repeat of the edit box status after several press on the up or down key.
- **Voice commands:**
 - The voice command “create a note” followed by the text of the note doesn’t save anymore automatically the note but stay on the Edit box for adding text or text correction purpose. Press “OK” key to save the note.

Application improvements:

- **Settings:**
 - Vocalisation / Wake up Speech: Now the day of the week is announced when Current date option is ticked.
- **Phone:**
 - It is now possible to answer an incoming call by using * or # keys when “Call pick-up with keys 0-9” option is set (see Settings / Keypad).

- Possibility to create a new message from call history.
- USSD code improvement.
- **Messages:**
 - New option to reset Access Point Names (APN).
 - Access Point Name (APN) data base has been updated to be more compatible with exotic network providers.
- **Contacts:**
 - “Delete all” contacts item has been moved at the end of the list to avoid errors.
 - Correction of the problem of customized ringtone for a contact.
 - Correction of the problem of missing name field when sending a contact through a message.
- **Notes:**
 - Empty notes are not saved automatically anymore.
 - Confirmation message has been added when a note has been copied or deleted.
- **Color Detector:**
 - The Color Detector application uses now a new engine based on artificial intelligence. To improve the performance of the detection, you must now use the silicone protective case provided in option and put the rear camera in contact with the object to know its color.

New feature:

- **Banknote recognizer**

The Banknote recognizer application allows you to use the MiniVision camera to identify the value of your bank notes. To optimize the detection, it is advised to position the unfolded bank note flat on a flat surface and position the phone between 20 and 30 cm from the target in a sufficiently bright environment. When the MiniVision’s camera detects the bank note, its value is automatically announced and displayed on the screen. At this time this application identifies only Euro Banknotes, and update will be proposed later on for new currencies.