

MiniVision2+

Release note – software version n° MV2+_11270

Software Update Process

An Internet connection is required to download and install MiniVision2+ updates. To update your device, go to “Settings”, select "About Phone" and then "System Updates". Select "Download and install" and press the "OK" button to start the download.

Depending on your connection, downloading the update may take some time. When the download is complete, select "Install" from the system update screen. It may take a few minutes to complete the process before you could use the product (vocalized feedback).

Improvements:

- **Overview:**
 - APN update.
- **System:**
 - The volume adjustment screen closes automatically after 10 seconds of inactivity (instead of 5 seconds). You can still close this screen at any time by pressing the OK button or the Back button.
 - New voices: MiniVision2+ now comes with new, higher-quality synthetic voices. These new voices are available from Settings > Vocalization > Voice choice. To benefit from these new voices and delete the old ones, the user must choose:
 - Uncheck the “Premium Voice” option from the phone’s vocalization settings.
 - Change the MiniVision2+ language.
 - Perform a full factory reset.

After each language or voice change, the phone will automatically restart to complete the installation process.

Warning: It is important to note that installing the new voices will permanently remove the old voice synthesis. If any of the above actions have been performed, it will no longer be possible to recover old voices. No voice change will be applied automatically after the software update in order to leave the user the choice of speech synthesis.

- Factory reset: you can now have access to the factory reset option from Settings > About phone > Factory reset. (same as the reset code *#333#).

Applications:

- **Alarm:**
 - The next alarm vocalization is now correctly stopped when you exit the application with the Home or Back keys.
 - When the alarm is ringing, using Up or Down keys will stop the ringtone of the alarm.
 - Correction of an issue where the alarm did not ring at the correct time.

- **Banknote:**
 - Ukrainian currency is now supported by the Banknote application.
- **Contacts:**
 - Service phone numbers from the SIM card are no more displayed by default.
- **Phone:**
 - Call waiting: Improvement of the feature:
 - When you are in communication and a second call is received, MiniVision2 will play a notification through the receiver to inform you. Press OK to take the second call and put the first caller in hold.
 - The first caller is no longer put automatically in hold when the second call is received.