

MiniVision2+

Release note – software version n° 12481

Software Update Process

An Internet connection is required to download and install MiniVision2+ updates.

- To update your device, go to “Settings”, select "About Phone" and then "System Updates".

Select "Download and install" and press the "OK" button to start the download.

Depending on your connection, downloading the update may take some time. When the download is complete, select "Install" from the system update screen. It may take a few minutes to complete the process before you could use the product (vocalized feedback).

Improvements:

- **Overview:**
 - Bug fixes.
 - Performance improvements.
 - Enhanced translations, voice guidance, and voice commands.
- **System:**
 - Fixed a bug that randomly caused the phone to freeze and restart.
 - Fixed a bug that sometimes prevented adjusting the screen brightness.
 - Non-compliant SD cards can now be formatted by the MiniVision2+ and used as main storage. Once the card is inserted and formatted, photos, voice memos, and other content will be stored there by default.
 - Fixed a bug that required SIM card unlocking when the option “Lock screen with star” was enabled.
- **Vocalization:**
 - Wake-up Announcements: This feature automatically provides certain information each time the device wakes from standby. Three new options are now available:
 - Next alarm.
 - Next calendar event.
 - Ringtone status (On or silent).

To enable these options: go to Settings > Vocalization > Wake-up announcement.

Applications:

- **Contacts:**
 - Contacts stored on the SIM card are no longer considered for incoming and outgoing calls, nor in the call history. Only contacts saved in the phone's internal memory are visible and available.
- **Banknote:**
 - Added recognition of British Pounds (GBP).
- **Messages:**
 - A new option is available in the Messages app: “Mark all messages as read”, accessible from the Menu key on the main screen. This option removes the “Unread” indication from all received messages